

SQL Sentry Audit Conditions

Last Modified on 18 May 2021


Audit Conditions are applicable to various activities inside and outside of the SQL Sentry client. **Audit Conditions** provide a way to be notified when various settings are changed, or monitored objects are modified from within the SQL Sentry client. **Audit Conditions have an assigned default severity and associated tags, and will affect your environment's Environmental Health Score (EHO).**

Note: The **Log to Database** action is configured by default for all **Audit Conditions**. This gives you an audit trail concerning changes to your SQL Sentry environment. If you'd like to be notified about **Audit Conditions** happening in your environment, configure the **Send Email Action**.


Configuring Actions for Audit Conditions

To add a Audit Condition, complete the following steps:



1. Open the **Navigator** pane (**View > Navigator**), and then select the desired node where you want to configure an action.



2. Open the Conditions Pane (**View > Conditions**) and then select **Audit Conditions** from the dropdown menu.



3. Select **Add** in the **Conditions** pane to open the **Actions Selector**. Expand the applicable object and condition. Use the checkbox(es) to select which actions should be taken in response to this condition being met, and then select **OK**.



[Additional Information:](#) For more information about actions that can be taken when a condition is met, see the [Actions](#) topic.

For a complete listing of all [Audit Conditions](#), see the following tables.

Event Chain

Condition	Description
Audit: Event Chain Created	An <u>Event Chain</u> is created.

Audit: Event Chain Deleted Condition	An Event Chain is deleted. Description
Audit: Event Chain Modified	An Event Chain is modified.

Global

Condition	Description
Audit: Actions Changed	A configured action is changed for an object.
Audit: Event Object Created	An Event Object (job, task, etc.) is created.
Audit: Event Object Deleted	An Event Object (job, task, etc.) is deleted.
Audit: Event Object Properties Modified	An Event Object's (job, task, etc.) properties are modified.
Audit: Event Object Rescheduled	An Event Object (job, task, etc.) is rescheduled. For some object types, this condition is only detected when rescheduling in the SQL Sentry client by dragging-and-dropping.
Audit: Notes Changed	A note is changed.
Audit: Settings Changed	Object or application settings are changed.
Audit: Watched Flag Changed	The watched flag is changed for an object.

Performance Counter

Condition	Description
Audit: Performance Counter Added	A Performance Counter is added to an event object or event view.
Audit: Performance Counter Deleted	A Performance Counter is deleted from an event object or event view.
Audit: Performance Monitored Flag Changed	The Performance Monitored flag is changed for an event object or event view.